

# Etching The IVCam Way

Etching in 4 Quick Steps

Quick & Simple


# Step One

- Select your image (*This image can be anything from a drawing to a photograph*)
- Load the image onto your Pc (*making sure it is in jpeg format*)
- Load up IVCam Handheld and Open your image



# Step 2

- Click on the "Edge Detector Tool" (*this option can be accessed either in the "Profile" menu Entitled "Auto Profile Options" or on your task bar*)
  
- Now pick the part of the image you wish to use (*Using the "Select Region of interest or else the entire image is assumed" you can select the image area you want to cover, by clicking and dragging over the area*)
  
- Select the curve/line length you wish to use (*The settings will allow you to change the amount of detail that will be picked up by the tool*)



# Step 3

- Now Click "Run extract lines or curves" (*If you wish to make any changes or to redo the line extraction you can click on the "Delete All Splines" option that is within this menu and try again*)
- When the desired lines are drawn click OK



# Step 4

- Export the Lines (*you are now ready to import the lines to CAD or which ever medium you want*)

